



Windows PowerShell Get-Help on Cmdlet 'Remove-AzTrafficManagerEndpointConfig'

PS:\>Get-HELP Remove-AzTrafficManagerEndpointConfig -Full

NAME

Remove-AzTrafficManagerEndpointConfig

SYNOPSIS

Removes an endpoint from a local Traffic Manager profile object.

SYNTAX

```

Remove-AzTrafficManagerEndpointConfig [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -EndpointName
<System.String> -TrafficManagerProfile <Microsoft.Azure.Commands.TrafficManager.Models.TrafficManagerProfile>
[<CommonParameters>]

```

DESCRIPTION

The Remove-AzTrafficManagerEndpointConfig cmdlet removes an endpoint from a local Azure Traffic Manager profile object. You can get a profile by using the Get-AzTrafficManagerProfile cmdlet.

This cmdlet operates on the local profile object. Commit your changes to the profile for Traffic Manager by using the

Set-AzTrafficManagerProfile cmdlet. To remove an

endpoint and commit changes in a single operation, use the Remove-AzTrafficManagerEndpoint cmdlet.

PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-EndpointName <System.String>

Specifies the name of the Traffic Manager endpoint that this cmdlet removes.

Required? true

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-TrafficManagerProfile <Microsoft.Azure.Commands.TrafficManager.Models.TrafficManagerProfile>

Specifies a local TrafficManagerProfile object. This cmdlet modifies this local object. To obtain a TrafficManagerProfile object, use the

Get-AzTrafficManagerProfile cmdlet.

Required? true

Position? named

Default value None

Accept pipeline input? True (ByValue)

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see [about_CommonParameters \(https://go.microsoft.com/fwlink/?LinkID=113216\)](https://go.microsoft.com/fwlink/?LinkID=113216).

INPUTS

Microsoft.Azure.Commands.TrafficManager.Models.TrafficManagerProfile

OUTPUTS

Microsoft.Azure.Commands.TrafficManager.Models.TrafficManagerProfile

NOTES

----- Example 1: Remove an endpoint -----

```
$TrafficManagerProfile = Get-AzTrafficManagerProfile -Name "ContosoProfile" -ResourceGroupName "ResourceGroup11"
Remove-AzTrafficManagerEndpointConfig -EndpointName "contoso" -TrafficManagerProfile $TrafficManagerProfile
Set-AzTrafficManagerProfile -TrafficManagerProfile $TrafficManagerProfile
```

The first command gets an Azure Traffic Manager profile by using the Get-AzTrafficManagerProfile cmdlet. The command stores the local profile in the \$TrafficManagerProfile variable.

The second command removes an Azure endpoint named contoso from the profile stored in \$TrafficManagerProfile. This command changes only the local object.

The final command updates the Traffic Manager profile named ContosoProfile to match the local value in \$TrafficManagerProfile.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.trafficmanager/remove-aztrafficmanagerendpointconfig>

Add-AzTrafficManagerEndpointConfig

Get-AzTrafficManagerProfile

Remove-AzTrafficManagerEndpoint

Set-AzTrafficManagerProfile