



Windows PowerShell Get-Help on Cmdlet 'Remove-AzVirtualNetworkGatewayDefaultSite'

PS:\>Get-HELP Remove-AzVirtualNetworkGatewayDefaultSite -Full

WARNING: The names of some imported commands from the module 'Microsoft.Azure.PowerShell.Cmdlets.Network' include unapproved verbs that might make them less discoverable.

To find the commands with unapproved verbs, run the Import-Module command again with the Verbose parameter. For a list of approved verbs, type Get-Verb.

NAME

Remove-AzVirtualNetworkGatewayDefaultSite

SYNOPSIS

Removes the default site from a virtual network gateway.

SYNTAX

```

Remove-AzVirtualNetworkGatewayDefaultSite [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>]
-VirtualNetworkGateway <Microsoft.Azure.Commands.Network.Models.PSVirtualNetworkGateway>
[<CommonParameters>]

```

DESCRIPTION

The Remove-AzVirtualNetworkGatewayDefaultSite cmdlet removes the forced tunneling default site from a virtual

network gateway. Forced tunneling provides a way for you

to redirect Internet-bound traffic from Azure virtual machines to your on-premises network; this enables you to inspect and audit traffic before releasing it. Forced

tunneling is carried out by using a virtual private network (VPN) tunnel; this tunnel requires a default site, a local gateway where all the Azure Internet-bound

traffic is redirected. Remove-AzVirtualNetworkGatewayDefaultSite removes the default site assigned to a gateway. If you do this you will need to use

Set-AzVirtualNetworkGatewayDefaultSite to assign a new default site before the gateway can be used for forced tunneling.

PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-VirtualNetworkGateway <Microsoft.Azure.Commands.Network.Models.PSVirtualNetworkGateway>

Specifies an object reference to the virtual network gateway containing the default site to be removed. You can create an object reference to a virtual network

gateway by using the Get-AzVirtualNetworkGateway and specifying the name of the gateway.

Required? true

Position? named

Default value None

Accept pipeline input? True (ByValue)

Accept wildcard characters? false

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see [about_CommonParameters \(https://go.microsoft.com/fwlink/?LinkID=113216\)](https://go.microsoft.com/fwlink/?LinkID=113216).

INPUTS

Microsoft.Azure.Commands.Network.Models.PSVirtualNetworkGateway

OUTPUTS

Microsoft.Azure.Commands.Network.Models.PSVirtualNetworkGateway

NOTES

Example 1: Remove the default site assigned to a virtual network gateway

```
$Gateway = Get-AzVirtualNetworkGateway -Name "ContosoVirtualGateway"
```

```
Remove-AzVirtualNetworkGatewayDefaultSite -VirtualNetworkGateway $Gateway
```

This example removes the default site currently assigned to a virtual network gateway named ContosoVirtualGateway. The first command uses `Get-AzVirtualNetworkGateway` to create an object reference to the gateway; this object reference is stored in a variable named `$Gateway`. The second command then uses

`Remove-AzVirtualNetworkGatewayDefaultSite` to remove the default site assigned to that gateway.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.network/remove-azvirtualnetworkgatewaydefaultsite>

`Get-AzVirtualNetworkGateway`

`Set-AzVirtualNetworkGatewayDefaultSite`