



Windows PowerShell Get-Help on Cmdlet 'Remove-AzVmssNetworkInterfaceConfiguration'

PS:\>Get-HELP Remove-AzVmssNetworkInterfaceConfiguration -Full

NAME

Remove-AzVmssNetworkInterfaceConfiguration

SYNOPSIS

Removes a network interface configuration from a VMSS.

SYNTAX

```

Remove-AzVmssNetworkInterfaceConfiguration [-VirtualMachineScaleSet]
<Microsoft.Azure.Commands.Compute.Automation.Models.PSVirtualMachineScaleSet> [-Id]
<System.String> [-DefaultProfile]
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer> [-Confirm] [-WhatIf]
[<CommonParameters>]

```

```

Remove-AzVmssNetworkInterfaceConfiguration [-VirtualMachineScaleSet]
<Microsoft.Azure.Commands.Compute.Automation.Models.PSVirtualMachineScaleSet> [-Name]
<System.String> [-DefaultProfile]
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer> [-Confirm] [-WhatIf]
[<CommonParameters>]

```

DESCRIPTION

The Remove-AzVmssNetworkInterfaceConfiguration cmdlet removes a network interface configuration from a Virtual Machine Scale Set (VMSS).

PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Id <System.String>

Specifies the ID of the network interface configuration that this cmdlet removes.

Required? true

Position? 1

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-Name <System.String>

Specifies the name of the network interface configuration that this cmdlet removes.

Required? true

Position? 1

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-VirtualMachineScaleSet <Microsoft.Azure.Commands.Compute.Automation.Models.PSVirtualMachineScaleSet>

Specifies the VMSS object.

Required? true

Position? 0

Default value None

Accept pipeline input? True (ByPropertyName, ByValue)

Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

Microsoft.Azure.Commands.Compute.Automation.Models.PSVirtualMachineScaleSet

System.String

OUTPUTS

Microsoft.Azure.Commands.Compute.Automation.Models.PSVirtualMachineScaleSet

NOTES

----- Example 1: Remove an interface configuration -----

```
$VMSS = Get-AzVmss -ResourceGroupName "ResourceGroup11" -VMScaleSetName "ContosoVMSS14"
```

```
Remove-AzVmssNetworkInterfaceConfiguration -VirtualMachineScaleSet $VMSS -Name "ContosoVmssInterface02"
```

The first command gets a VMSS by using the Get-AzVmss cmdlet, and then stores it in the \$VMSS variable. The second command removes the network interface configuration

named ContosoVmssInterface02 from the set in \$VMSS.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.compute/remove-azvmssnetworkinterfaceconfiguration>

Add-AzVmssNetworkInterfaceConfiguration

