



Windows PowerShell Get-Help on Cmdlet 'Revoke-AzDiskAccess'

PS:\>Get-HELP Revoke-AzDiskAccess -Full

NAME

Revoke-AzDiskAccess

SYNOPSIS

Revokes an access to a disk.

SYNTAX

Revoke-AzDiskAccess [-ResourceGroupName] <System.String> [-DiskName] <System.String> [-AsJob] [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Confirm] [-WhatIf]
[<CommonParameters>]

DESCRIPTION

The Revoke-AzDiskAccess cmdlet revokes an access to a disk.

PARAMETERS

-AsJob <System.Management.Automation.SwitchParameter>

Run cmdlet in the background

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with azure.

Required? false
Position? named
Default value None
Accept pipeline input? False
Accept wildcard characters? false

-DiskName <System.String>

Specifies the name of a disk.

Required? true
Position? 1
Default value None
Accept pipeline input? True (ByPropertyName)
Accept wildcard characters? false

-ResourceGroupName <System.String>

Specifies the name of a resource group.

Required? true
Position? 0
Default value None
Accept pipeline input? True (ByPropertyName)
Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

System.String

OUTPUTS

Microsoft.Azure.Commands.Compute.Automation.Models.PSOperationStatusResponse

NOTES

----- Example 1 -----

```
Revoke-AzDiskAccess -ResourceGroupName 'ResourceGroup01' -DiskName 'Disk01'
```

Revoke the access to the disk named 'Disk01' in the resource group named 'ResourceGroup01'

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.compute/revoke-azdiskaccess>