



Windows PowerShell Get-Help on Cmdlet 'Set-AzDataLakeStoreItemOwner'

PS:\>Get-HELP Set-AzDataLakeStoreItemOwner -Full

NAME

Set-AzDataLakeStoreItemOwner

SYNOPSIS

Modifies the owner of a file or folder in Data Lake Store.

SYNTAX

```

Set-AzDataLakeStoreItemOwner [-Account] <System.String> [-Path]
<Microsoft.Azure.Commands.DataLakeStore.Models.DataLakeStorePathInstance> [-Type] {User | Group} [-Id]
<System.Guid> [-DefaultProfile]
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-PassThru] [-Confirm]
[-WhatIf]
[<CommonParameters>]

```

DESCRIPTION

The Set-AzDataLakeStoreItemOwner cmdlet modifies the owner of a file or folder in Data Lake Store.

PARAMETERS

-Account <System.String>

Specifies the name of the Data Lake Store account.

Required? true

Position? 0

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Id <System.Guid>

Specifies the object ID of the AzureActive Directory user, group, or service principal to use as the owner.

Required? true

Position? 3

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-PassThru <System.Management.Automation.SwitchParameter>

Indicates the resulting updated owner should be returned.

Required? false

Position? named

Default value False

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-Path <Microsoft.Azure.Commands.DataLakeStore.Models.DataLakeStorePathInstance>

Specifies the Data Lake Store path of the item to modify, starting with the root directory (/).

Required? true

Position? 1

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-Type <Microsoft.Azure.Commands.DataLakeStore.Models.DataLakeStoreEnums+Owner>

Specifies the type of owner to set. The acceptable values for this parameter are: User and Group.

Required? true

Position? 2

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required?	false
Position?	named
Default value	False
Accept pipeline input?	False
Accept wildcard characters?	false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

System.String

Microsoft.Azure.Commands.DataLakeStore.Models.DataLakeStorePathInstance

Microsoft.Azure.Commands.DataLakeStore.Models.DataLakeStoreEnums+Owner

System.Guid

System.Management.Automation.SwitchParameter

OUTPUTS

System.String

NOTES

----- Example 1: Set the owner for an item -----

```
Set-AzDataLakeStoreItemOwner -AccountName "ContosoADL" -Path / -Type User -Id (Get-AzADUser -Mail  
"PattiFuller@contoso.com").ObjectId
```

This command sets the owner for the root directory to Patti Fuller.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.datalakestore/set-azdatalakestoreitemowner>

Get-AzDataLakeStoreItemOwner