



Windows PowerShell Get-Help on Cmdlet 'Set-AzKeyVaultCertificateIssuer'

PS:\>Get-HELP Set-AzKeyVaultCertificateIssuer -Full

NAME

Set-AzKeyVaultCertificateIssuer

SYNOPSIS

Sets a certificate issuer in a key vault.

SYNTAX

```
Set-AzKeyVaultCertificateIssuer [-VaultName] <System.String> [-Name] <System.String> [-AccountId <System.String>]
[-ApiKey <System.Security.SecureString>]
[-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>]
-IssuerProvider <System.String> [-OrganizationDetails
<Microsoft.Azure.Commands.KeyVault.Models.PSKeyVaultCertificateOrganizationDetails>] [-PassThru] [-Confirm]
[-WhatIf] [<CommonParameters>]
```

```
Set-AzKeyVaultCertificateIssuer [-VaultName] <System.String> [-Name] <System.String> [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -InputObject
<Microsoft.Azure.Commands.KeyVault.Models.PSKeyVaultCertificateIssuerIdentityItem> [-PassThru] [-Confirm] [-WhatIf]
[<CommonParameters>]
```

DESCRIPTION

The Set-AzKeyVaultCertificateIssuer cmdlet sets a certificate issuer in a key vault.

PARAMETERS

-AccountId <System.String>

Specifies the account ID for the certificate issuer.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-ApiKey <System.Security.SecureString>

Specifies the API key for the certificate issuer.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with azure

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-InputObject <Microsoft.Azure.Commands.KeyVault.Models.PSKeyVaultCertificateIssuerIdentityItem>

Specifies the certificate issuer to set.

Required? true

Position? named

Default value None

Accept pipeline input? True (ByValue)

Accept wildcard characters? false

-IssuerProvider <System.String>

Specifies the type of certificate issuer.

Required? true

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Name <System.String>

Specifies the name of the Issuer.

Required? true

Position? 1

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-OrganizationDetails <Microsoft.Azure.Commands.KeyVault.Models.PSKeyVaultCertificateOrganizationDetails>

Organization details to be used with the issuer.

Required? false

Position? named

Default value None

Accept pipeline input? True (ByValue)

Accept wildcard characters? false

-PassThru <System.Management.Automation.SwitchParameter>

Returns an object representing the item with which you are working. By default, this cmdlet does not generate any output.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-VaultName <System.String>

Specifies the name of the key vault.

Required? true

Position? 0

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required?	false
Position?	named
Default value	False
Accept pipeline input?	False
Accept wildcard characters?	false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

Microsoft.Azure.Commands.KeyVault.Models.PSKeyVaultCertificateOrganizationDetails

Microsoft.Azure.Commands.KeyVault.Models.PSKeyVaultCertificateIssuerIdentityItem

OUTPUTS

Microsoft.Azure.Commands.KeyVault.Models.PSKeyVaultCertificatePolicy

NOTES

----- Example 1: Set a certificate issuer -----

```
$AdminDetails = New-AzKeyVaultCertificateAdministratorDetail -FirstName user -LastName name -EmailAddress  
username@microsoft.com  
  
$OrgDetails = New-AzKeyVaultCertificateOrganizationDetail -AdministratorDetails $AdminDetails  
  
$Password = ConvertTo-SecureString -String P@ssw0rd -AsPlainText -Force  
  
Set-AzKeyVaultCertificateIssuer -VaultName "Contosokv01" -Name "TestIssuer01" -IssuerProvider "Test" -Accountld  
"555" -ApiKey $Password -OrganizationDetails  
$OrgDetails -PassThru
```

Accountld : 555

ApiKey :

OrganizationDetails : Microsoft.Azure.Commands.KeyVault.Models.PSKeyVaultCertificateOrganizationDetails

Name : TestIssuer01

IssuerProvider : Test

VaultName : Contosokv01

This command sets the properties for a certificate issuer.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.keyvault/set-azkeyvaultcertificateissuer>

Get-AzKeyVaultCertificateIssuer

Remove-AzKeyVaultCertificateIssuer