



Windows PowerShell Get-Help on Cmdlet 'Set-AzNetworkInterfaceTapConfig'

PS: \> Get-HELP Set-AzNetworkInterfaceTapConfig -Full

WARNING: The names of some imported commands from the module 'Microsoft.Azure.PowerShell.Cmdlets.Network' include unapproved verbs that might make them less discoverable.

To find the commands with unapproved verbs, run the Import-Module command again with the Verbose parameter. For a list of approved verbs, type Get-Verb.

NAME

Set-AzNetworkInterfaceTapConfig

SYNOPSIS

Updates a tap configuration for a network interface.

SYNTAX

```
Set-AzNetworkInterfaceTapConfig [-AsJob] [-DefaultProfile  
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Force]  
-NetworkInterfaceTapConfig <Microsoft.Azure.Commands.Network.Models.PSNetworkInterfaceTapConfiguration>  
[-Confirm] [-WhatIf] [<CommonParameters>]
```

DESCRIPTION

The Set-AzNetworkInterfaceTapConfig updates a tap configuration for a network interface.

PARAMETERS

-AsJob <System.Management.Automation.SwitchParameter>

Run cmdlet in the background

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Force <System.Management.Automation.SwitchParameter>

Do not ask for confirmation.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-NetworkInterfaceTapConfig <Microsoft.Azure.Commands.Network.Models.PSNetworkInterfaceTapConfiguration>

The NetworkInterface Tap configuration

Required? true
Position? named
Default value None
Accept pipeline input? True (ByValue)
Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see [about_CommonParameters \(https://go.microsoft.com/fwlink/?LinkID=113216\)](https://go.microsoft.com/fwlink/?LinkID=113216).

INPUTS

Microsoft.Azure.Commands.Network.Models.PSNetworkInterfaceTapConfiguration

OUTPUTS

Microsoft.Azure.Commands.Network.Models.PSNetworkInterface

NOTES

Example 1: Set the TapConfiguration with updated TapConfig name

```
$tapConfig = Get-AzNetworkInterfaceTapConfig -ResourceGroupName "ResourceGroup1" -NetworkInterfaceName  
"sourceNicName" -Name "tapconfigName"  
$tapConfig.Name = "NewTapName"  
Set-AzNetworkInterfaceTapConfig -NetworkInterfaceTapConfig $tapConfig
```

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.network/set-aznetworkinterfacetapconfig>

Add-AzNetworkInterfaceTapConfig

Get-AzNetworkInterfaceTapConfig

Remove-AzNetworkInterfaceTapConfig