



Windows PowerShell Get-Help on Cmdlet 'Set-AzSecurityAutoProvisioningSetting'

PS:\>Get-HELP Set-AzSecurityAutoProvisioningSetting -Full

NAME

Set-AzSecurityAutoProvisioningSetting

SYNOPSIS

Updates automatic provisioning setting

SYNTAX

Set-AzSecurityAutoProvisioningSetting [-DefaultProfile

<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>]

[-EnableAutoProvision] -Name <System.String> [-Confirm] [-WhatIf] [<CommonParameters>]

Set-AzSecurityAutoProvisioningSetting [-DefaultProfile

<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>]

[-EnableAutoProvision] -ResourceId <System.String> [-Confirm] [-WhatIf] [<CommonParameters>]

Set-AzSecurityAutoProvisioningSetting [-DefaultProfile

<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -InputObject

<Microsoft.Azure.Commands.Security.Models.AutoProvisioningSettings.PSSecurityAutoProvisioningSetting> [-Confirm]

[-WhatIf] [<CommonParameters>]

DESCRIPTION

Turns on or off automatic provisioning settings for a subscription. Automatic Provisioning Settings let you decide whether you want Azure Security Center to automatically provision a security agent that will be installed on your VMs. The security agent will monitor your VM to create security alerts and monitor the security compliance of the VM.

PARAMETERS

`-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>`

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

`-EnableAutoProvision <System.Management.Automation.SwitchParameter>`

Automatic Provisioning.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-InputObject

`<Microsoft.Azure.Commands.Security.Models.AutoProvisioningSettings.PSSecurityAutoProvisioningSetting>`

Input Object.

Required? true
Position? named
Default value None
Accept pipeline input? True (ByValue)
Accept wildcard characters? false

-Name <System.String>

Resource name.

Required? true
Position? named
Default value None
Accept pipeline input? False
Accept wildcard characters? false

-ResourceId <System.String>

Resource ID.

Required? true
Position? named
Default value None
Accept pipeline input? True (ByPropertyName)
Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

System.String

Microsoft.Azure.Commands.Security.Models.AutoProvisioningSettings.PSSecurityAutoProvisioningSetting

OUTPUTS

Microsoft.Azure.Commands.Security.Models.AutoProvisioningSettings.PSSecurityAutoProvisioningSetting

NOTES

----- Example 1 -----

Set-AzSecurityAutoProvisioningSetting -Name "default" -EnableAutoProvision

Id	Name	AutoProvision
----	------	---------------

--	----	-----
----	------	-------

/subscriptions/487bb485-b5b0-471e-9c0d-10717612f869/providers/Microsoft.Security/autoProvisioningSettings/default

default On

Turns on automatic provisioning setting for a subscription.

----- Example 2 -----

Set-AzSecurityAutoProvisioningSetting -Name "default"

Id	Name
----	------

--	----
----	------

/subscriptions/487bb485-b5b0-471e-9c0d-10717612f869/providers/Microsoft.Security/autoProvisioningSettings/default

de...

Turns off automatic provisioning setting for a subscription.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.security/Set-AzSecurityAutoProvisioningSetting>