



Windows PowerShell Get-Help on Cmdlet 'Set-AzServiceFabricUpgradeType'

PS:\>Get-HELP Set-AzServiceFabricUpgradeType -Full

NAME

Set-AzServiceFabricUpgradeType

SYNOPSIS

Change the Service Fabric upgrade type of the cluster.

SYNTAX

```
Set-AzServiceFabricUpgradeType [-ResourceGroupName] <System.String> [-Name] <System.String> [-DefaultProfile  
    <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -UpgradeMode  
{Automatic | Manual} -Version <System.String> [-Confirm]  
[-WhatIf] [<CommonParameters>]
```

DESCRIPTION

Use Set-AzServiceFabricUpgradeType to set upgrade type to automatic or manual with specific Service Fabric code version.

PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Name <System.String>

Specify the name of the cluster

Required? true

Position? 1

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-ResourceGroupName <System.String>

Specify the name of the resource group.

Required? true

Position? 0

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-UpgradeMode <Microsoft.Azure.Commands.ServiceFabric.Models.ClusterUpgradeMode>

ClusterUpgradeMode

Required? true

Position? named

Default value None

Accept pipeline input? True (ByValue)

Accept wildcard characters? false

-Version <System.String>

Cluster code version

Required? true

Position? named

Default value None

Accept pipeline input? True (ByValue)

Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable,

OutBuffer, PipelineVariable, and OutVariable. For more information, see
about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

System.String

Microsoft.Azure.Commands.ServiceFabric.Models.ClusterUpgradeMode

OUTPUTS

Microsoft.Azure.Commands.ServiceFabric.Models.PSCluster

NOTES

----- Example 1 -----

```
Set-AzServiceFabricUpgradeType -ResourceGroupName 'Group1' -Name 'Contoso01SFCluster' -UpgradeMode  
Automatic
```

This command will set the cluster upgrade mode to automatic.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.servicefabric/set-azservicefabricupgradetype>

