



Windows PowerShell Get-Help on Cmdlet 'Set-BcdDebugSettings'

PS:\>Get-HELP Set-BcdDebugSettings -Full

NAME

Set-BcdDebugSettings

SYNTAX

Set-BcdDebugSettings [[-Store] <BcdStoreInfo>] -DebugPort <long> -Serial [-Baudrate <long>] [-StartPolicy {Active | AutoEnable | Disable}] [-NoUserModeExceptions]

[-Force] [<CommonParameters>]

Set-BcdDebugSettings [[-Store] <BcdStoreInfo>] -Serial [-StartPolicy {Active | AutoEnable | Disable}] [-NoUserModeExceptions] [-Force] [<CommonParameters>]

Set-BcdDebugSettings [[-Store] <BcdStoreInfo>] -Port <long> -HostIp <string> -Net -Key <string> [-NoDhcp] [-StartPolicy {Active | AutoEnable | Disable}]

[-NoUserModeExceptions] [-Force] [<CommonParameters>]

Set-BcdDebugSettings [[-Store] <BcdStoreInfo>] -Port <long> -HostIp <string> -Net [-NewKey] [-NoDhcp] [-StartPolicy {Active | AutoEnable | Disable}]

[-NoUserModeExceptions] [-Force] [<CommonParameters>]

Set-BcdDebugSettings [[-Store] <BcdStoreInfo>] -Channel <long> -Ieee1394 [-StartPolicy {Active | AutoEnable | Disable}]

[-NoUserModeExceptions] [-Force]

[<CommonParameters>]

Set-BcdDebugSettings [[-Store] <BcdStoreInfo>] -Usb [-TargetName <string>] [-StartPolicy {Active | AutoEnable | Disable}] [-NoUserModeExceptions] [-Force]

[<CommonParameters>]

Set-BcdDebugSettings [[-Store] <BcdStoreInfo>] -Local [-StartPolicy {Active | AutoEnable | Disable}] [-NoUserModeExceptions] [-Force] [<CommonParameters>]

PARAMETERS

-Baudrate <long>

Required?	false
Position?	Named
Accept pipeline input?	false
Parameter set name	SerialWithDebugPort
Aliases	None
Dynamic?	false

-Channel <long>

Required?	true
Position?	Named
Accept pipeline input?	false
Parameter set name	1394
Aliases	None
Dynamic?	false

-DebugPort <long>

Required?	true
-----------	------

Position?	Named
Accept pipeline input?	false
Parameter set name	SerialWithDebugPort
Aliases	None
Dynamic?	false

-Force

Required?	false
Position?	Named
Accept pipeline input?	false
Parameter set name	(All)
Aliases	None
Dynamic?	false

-HostIp <string>

Required?	true
Position?	Named
Accept pipeline input?	false
Parameter set name	NETWithKey, NETCreateKey
Aliases	None
Dynamic?	false

-leee1394

Required?	true
Position?	Named
Accept pipeline input?	false
Parameter set name	1394
Aliases	None
Dynamic?	false

-Key <string>

Required?	true
Position?	Named
Accept pipeline input?	false
Parameter set name	NETWithKey
Aliases	None
Dynamic?	false

-Local

Required?	true
Position?	Named
Accept pipeline input?	false
Parameter set name	Local
Aliases	None
Dynamic?	false

-Net

Required?	true
Position?	Named
Accept pipeline input?	false
Parameter set name	NETWithKey, NETCreateKey
Aliases	None
Dynamic?	false

-NewKey

Required?	false
Position?	Named
Accept pipeline input?	false
Parameter set name	NETCreateKey

Aliases	None
Dynamic?	false

-NoDhcp

Required?	false
Position?	Named
Accept pipeline input?	false
Parameter set name	NETWithKey, NETCreateKey
Aliases	None
Dynamic?	false

-NoUserModeExceptions

Required?	false
Position?	Named
Accept pipeline input?	false
Parameter set name	SerialWithDebugPort, SerialWithOutDebugPort, NETWithKey, NETCreateKey, 1394, Usb,

Local

Aliases	NoUmex
Dynamic?	false

-Port <long>

Required?	true
Position?	Named
Accept pipeline input?	false
Parameter set name	NETWithKey, NETCreateKey
Aliases	None
Dynamic?	false

-Serial

Required?	true
Position?	Named
Accept pipeline input?	false
Parameter set name	SerialWithDebugPort, SerialWithOutDebugPort
Aliases	None
Dynamic?	false

-StartPolicy <StartPolicy>

Required?	false
Position?	Named
Accept pipeline input?	false
Parameter set name	SerialWithDebugPort, SerialWithOutDebugPort, NETWithKey, NETCreateKey, 1394, Usb,

Local

Aliases	None
Dynamic?	false

-Store <BcdStoreInfo>

Required?	false
Position?	0
Accept pipeline input?	true (ByValue, ByPropertyName)
Parameter set name	SerialWithDebugPort, SerialWithOutDebugPort, NETWithKey, NETCreateKey, 1394, Usb,

Local

Aliases	None
Dynamic?	false

-TargetName <string>

Required?	false
Position?	Named
Accept pipeline input?	false
Parameter set name	Usb

Aliases	None
Dynamic?	false

-Usb

Required?	true
Position?	Named
Accept pipeline input?	false
Parameter set name	Usb
Aliases	None
Dynamic?	false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

Microsoft.Windows.Bcd.Cmdlets.BcdExtensions.BcdStoreInfo

OUTPUTS

System.Object

ALIASES

None

REMARKS

None

