



Windows PowerShell Get-Help on Cmdlet 'Set-BcdHypervisorSettings'

PS:\>Get-HELP Set-BcdHypervisorSettings -Full

NAME

Set-BcdHypervisorSettings

SYNTAX

Set-BcdHypervisorSettings [[-Store] <BcdStoreInfo>] -DebugPort <long> -Serial [-Baudrate <long>] [-Force] [-WhatIf] [-Confirm] [<CommonParameters>]

Set-BcdHypervisorSettings [[-Store] <BcdStoreInfo>] -Ieee1394 [-Channel <long>] [-Force] [-WhatIf] [-Confirm] [<CommonParameters>]

Set-BcdHypervisorSettings [[-Store] <BcdStoreInfo>] -HostIp <string> -Port <long> -Net [-Force] [-WhatIf] [-Confirm] [<CommonParameters>]

Set-BcdHypervisorSettings [[-Store] <BcdStoreInfo>] -Serial [-Force] [-WhatIf] [-Confirm] [<CommonParameters>]

PARAMETERS

-Baudrate <long>

Required? false

Position?	Named
Accept pipeline input?	false
Parameter set name	SerialWithDebugPort
Aliases	None
Dynamic?	false

-Channel <long>

Required?	false
Position?	Named
Accept pipeline input?	false
Parameter set name	1394
Aliases	None
Dynamic?	false

-Confirm

Required?	false
Position?	Named
Accept pipeline input?	false
Parameter set name	(All)
Aliases	cf
Dynamic?	false

-DebugPort <long>

Required?	true
Position?	Named
Accept pipeline input?	false
Parameter set name	SerialWithDebugPort
Aliases	None
Dynamic?	false

-Force

Required?	false
Position?	Named
Accept pipeline input?	false
Parameter set name	(All)
Aliases	None
Dynamic?	false

-HostIp <string>

Required?	true
Position?	Named
Accept pipeline input?	false
Parameter set name	NET
Aliases	None
Dynamic?	false

-leee1394

Required?	true
Position?	Named
Accept pipeline input?	false
Parameter set name	1394
Aliases	None
Dynamic?	false

-Net

Required?	true
Position?	Named
Accept pipeline input?	false
Parameter set name	NET

Aliases	None
Dynamic?	false

-Port <long>

Required?	true
Position?	Named
Accept pipeline input?	false
Parameter set name	NET
Aliases	None
Dynamic?	false

-Serial

Required?	true
Position?	Named
Accept pipeline input?	false
Parameter set name	SerialWithDebugPort, SerialWithOutDebugPort
Aliases	None
Dynamic?	false

-Store <BcdStoreInfo>

Required?	false
Position?	0
Accept pipeline input?	true (ByValue, ByPropertyName)
Parameter set name	SerialWithDebugPort, 1394, NET, SerialWithOutDebugPort
Aliases	None
Dynamic?	false

-WhatIf

Required?	false
-----------	-------

Position?	Named
Accept pipeline input?	false
Parameter set name	(All)
Aliases	wi
Dynamic?	false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

Microsoft.Windows.Bcd.Cmdlets.BcdExtensions.BcdStoreInfo

OUTPUTS

System.Object

ALIASES

None

REMARKS

None