



Full credit is given to all the above companies including the Operating System that this PDF file was generated!

Windows PowerShell Get-Help on Cmdlet 'Set-DtcDefault'

PS:\>Get-HELP Set-DtcDefault -Full

NAME

Set-DtcDefault

SYNOPSIS

Sets the default transactions coordinator.

SYNTAX

```
Set-DtcDefault [-AsJob] [-CimSession <CimSession[]>] [-ServerName <String>] [-ThrottleLimit <Int32>]
[<CommonParameters>]
```

DESCRIPTION

The Set-DtcDefault cmdlet sets the default transactions coordinator.

PARAMETERS

-AsJob [<SwitchParameter>]

Runs the cmdlet as a background job. Use this parameter to run commands that take a long time to complete.

The cmdlet immediately returns an object that represents the job and then displays the command prompt. You can continue to work in the session while the job

completes. To manage the job, use the ``*-Job`` cmdlets. To get the job results, use the `Receive-Job` (<https://go.microsoft.com/fwlink/?LinkID=113372>) cmdlet.

For more information about Windows PowerShell background jobs, see `about_Jobs` (<https://go.microsoft.com/fwlink/?LinkID=113251>).

Required?	false
Position?	named
Default value	False
Accept pipeline input?	False
Accept wildcard characters?	false

`-CimSession <CimSession[]>`

Runs the cmdlet in a remote session or on a remote computer. Enter a computer name or a session object, such as the output of a `New-CimSession`

(<https://go.microsoft.com/fwlink/p/?LinkId=227967>) or

`[Get-CimSession]`(<https://go.microsoft.com/fwlink/p/?LinkId=227966>) cmdlet. The default is the current session on the local computer.

Required?	false
Position?	named
Default value	None
Accept pipeline input?	False
Accept wildcard characters?	false

`-ServerName <String>`

Specifies the host name or virtual server name of the Distributed Transaction Coordinator (DTC) to set as the default coordinator. If you do not specify this parameter, this cmdlet specifies the local DTC as the default coordinator.

Required?	false
-----------	-------

Position? named
Default value None
Accept pipeline input? False
Accept wildcard characters? false

-ThrottleLimit <Int32>

Specifies the maximum number of concurrent operations that can be established to run the cmdlet. If this parameter is omitted or a value of `0` is entered, then

Windows PowerShell calculates an optimum throttle limit for the cmdlet based on the number of CIM cmdlets that are running on the computer. The throttle limit applies only to the current cmdlet, not to the session or to the computer.

Required? false
Position? named
Default value None
Accept pipeline input? False
Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see [about_CommonParameters \(https://go.microsoft.com/fwlink/?LinkID=113216\)](https://go.microsoft.com/fwlink/?LinkID=113216).

INPUTS

OUTPUTS

NOTES

----- Example 1: Set the default DTC coordinator -----

```
PS C:\> Set-DtcDefault -ServerName "host14"
```

This command sets the default DTC coordinator to host14.

RELATED LINKS

Online

Version:

https://learn.microsoft.com/powershell/module/msdtc/set-dtcdefault?view=windowsserver2022-ps&wt.mc_id=ps-gethelp

Get-DtcDefault