



## ***Windows PowerShell Get-Help on Cmdlet 'Set-DtcTransactionsTraceSession'***

***PS:\>Get-HELP Set-DtcTransactionsTraceSession -Full***

### NAME

Set-DtcTransactionsTraceSession

### SYNOPSIS

Modifies the DTC transactions trace setting of the host.

### SYNTAX

Set-DtcTransactionsTraceSession [-AsJob] -BufferCount <UInt32> [-CimSession <CimSession[]>] [-ThrottleLimit <Int32>]  
[<CommonParameters>]

### DESCRIPTION

The Set-DtcTransactionsTraceSession cmdlet modifies the Distributed Transaction Coordinator (DTC) transactions trace setting of the host.

### PARAMETERS

-AsJob [<SwitchParameter>]

Runs the cmdlet as a background job. Use this parameter to run commands that take a long time to complete.

The cmdlet immediately returns an object that represents the job and then displays the command prompt. You can continue to work in the session while the job

completes. To manage the job, use the ``*-Job`` cmdlets. To get the job results, use the `Receive-Job` (<https://go.microsoft.com/fwlink/?LinkID=113372>) cmdlet.

For more information about Windows PowerShell background jobs, see `about_Jobs` (<https://go.microsoft.com/fwlink/?LinkID=113251>).

Required?	false
Position?	named
Default value	False
Accept pipeline input?	False
Accept wildcard characters?	false

`-BufferCount <UInt32>`

Specifies the number of buffers to use for a DTC transactions trace.

Required?	true
Position?	named
Default value	None
Accept pipeline input?	False
Accept wildcard characters?	false

`-CimSession <CimSession[]>`

Runs the cmdlet in a remote session or on a remote computer. Enter a computer name or a session object, such as the output of a `New-CimSession`

(<https://go.microsoft.com/fwlink/p/?LinkId=227967>) or `[Get-CimSession]` (<https://go.microsoft.com/fwlink/p/?LinkId=227966>) cmdlet. The default is the current session on the local computer.

Required?	false
Position?	named

Default value           None  
Accept pipeline input?   False  
Accept wildcard characters? false

#### **-ThrottleLimit <Int32>**

Specifies the maximum number of concurrent operations that can be established to run the cmdlet. If this parameter is omitted or a value of `0` is entered, then

Windows PowerShell calculates an optimum throttle limit for the cmdlet based on the number of CIM cmdlets that are running on the computer. The throttle limit

applies only to the current cmdlet, not to the session or to the computer.

Required?           false  
Position?           named  
Default value       None  
Accept pipeline input?   False  
Accept wildcard characters? false

#### **<CommonParameters>**

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see [about\\_CommonParameters \(https://go.microsoft.com/fwlink/?LinkID=113216\)](https://go.microsoft.com/fwlink/?LinkID=113216).

## **INPUTS**

## **OUTPUTS**

## **NOTES**

```
PS C:\> Set-DtcTransactionsTraceSession -BufferCount 32
```

This command sets the DTC transactions trace session buffer count to 32.

## RELATED LINKS

Online

Version:

[https://learn.microsoft.com/powershell/module/msdtc/set-dtctransactionstracesession?view=windowsserver2022-ps&wt.mc\\_id=ps-gethelp](https://learn.microsoft.com/powershell/module/msdtc/set-dtctransactionstracesession?view=windowsserver2022-ps&wt.mc_id=ps-gethelp)

Get-DtcTransactionsTraceSession

Start-DtcTransactionsTraceSession

Stop-DtcTransactionsTraceSession

Write-DtcTransactionsTraceSession