



**Full credit is given to all the above companies including the Operating System that this PDF file was generated!**

### ***Windows PowerShell Get-Help on Cmdlet 'Set-WinLanguageBarOption'***

**PS:\>Get-HELP Set-WinLanguageBarOption -Full**

#### **NAME**

Set-WinLanguageBarOption

#### **SYNOPSIS**

Sets the language bar type and mode for the current user account.

#### **SYNTAX**

Set-WinLanguageBarOption [-UseLegacyLanguageBar] [-UseLegacySwitchMode] [<CommonParameters>]

#### **DESCRIPTION**

The Set-WinLanguageBarOption cmdlet sets the language bar type and mode by using a LanguageBar object. The values for the type and mode settings can be either true or false. The default value for each setting is false.

#### **PARAMETERS**

**-UseLegacyLanguageBar [<SwitchParameter>]**

Indicates that this cmdlet sets the language bar mode to the legacy setting. If you do not specify this parameter, the

cmdlet sets the language bar mode to the default setting.

Required? false  
Position? named  
Default value False  
Accept pipeline input? False  
Accept wildcard characters? false

#### -UseLegacySwitchMode [<SwitchParameter>]

Indicates that this cmdlet sets the language bar switch mode to the legacy or per-thread setting. If you do not specify this parameter, the cmdlet sets the language bar switch mode to the default or per-user setting.

Required? false  
Position? named  
Default value False  
Accept pipeline input? False  
Accept wildcard characters? false

#### <CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about\_CommonParameters (<https://go.microsoft.com/fwlink/?LinkId=113216>).

## INPUTS

## OUTPUTS

## NOTES

----- Example 1: Set language bar options -----

```
PS C:\> Set-WinLanguageBarOption -UseLegacySwitchMode -UseLegacyLanguageBar
```

This command sets the language bar mode to the legacy setting and the language bar type to the per-thread setting.

--- Example 2: Set language bar options to default values ---

```
PS C:\> Set-WinLanguageBarOption
```

This command sets the language bar mode and the language bar type to the default setting.

## RELATED LINKS

Online

Version:

[https://learn.microsoft.com/powershell/module/international/set-winlanguagebaroption?view=windowsserver2022-ps&wt.mc\\_id=ps-gethelp](https://learn.microsoft.com/powershell/module/international/set-winlanguagebaroption?view=windowsserver2022-ps&wt.mc_id=ps-gethelp)

[Get-WinLanguageBarOption](#)