



Windows PowerShell Get-Help on Cmdlet 'Update-AzCosmosDBSqlContainerThroughput'

PS:\>Get-HELP Update-AzCosmosDBSqlContainerThroughput -Full

NAME

Update-AzCosmosDBSqlContainerThroughput

SYNOPSIS

Updates the throughput value of a CosmosDB Sql Container.

SYNTAX

```
Update-AzCosmosDBSqlContainerThroughput -AccountName <System.String> [-AutoscaleMaxThroughput
<System.Nullable`1[System.Int32]>] -DatabaseName <System.String>
[-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>]
[-Name <System.String>] -ResourceGroupName <System.String>
[-Throughput <System.Nullable`1[System.Int32]>] [-Confirm] [-WhatIf] [<CommonParameters>]

Update-AzCosmosDBSqlContainerThroughput [-AutoscaleMaxThroughput <System.Nullable`1[System.Int32]>]
[-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -InputObject
<Microsoft.Azure.Commands.CosmosDB.Models.PSSqlContainerGetResults> [-Name <System.String>] [-Throughput
<System.Nullable`1[System.Int32]>] [-Confirm] [-WhatIf]
[<CommonParameters>]
```

Update-AzCosmosDBSqlContainerThroughput [-AutoscaleMaxThroughput <System.Nullable`1[System.Int32]>]
 [-DefaultProfile
 <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Name
 <System.String>] -ParentObject
 <Microsoft.Azure.Commands.CosmosDB.Models.PSSqlDatabaseGetResults> [-Throughput
 <System.Nullable`1[System.Int32]>] [-Confirm] [-WhatIf] [<CommonParameters>]

DESCRIPTION

Updates the throughput value of a CosmosDB Sql Container.

PARAMETERS

-AccountName <System.String>

Name of the Cosmos DB database account.

Required? true

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-AutoscaleMaxThroughput <System.Nullable`1[System.Int32]>

Maximum Throughput value if autoscale is enabled.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-DatabaseName <System.String>

Database name.

Required?	true
Position?	named
Default value	None
Accept pipeline input?	False
Accept wildcard characters?	false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required?	false
Position?	named
Default value	None
Accept pipeline input?	False
Accept wildcard characters?	false

-InputObject <Microsoft.Azure.Commands.CosmosDB.Models.PSSqlContainerGetResults>

Sql Database object.

Required?	true
Position?	named
Default value	None
Accept pipeline input?	True (ByValue)
Accept wildcard characters?	false

-Name <System.String>

Container name.

Required?	false
Position?	named
Default value	None
Accept pipeline input?	False

Accept wildcard characters? false

-ParentObject <Microsoft.Azure.Commands.CosmosDB.Models.PSSqlDatabaseGetResults>

Sql Database object.

Required? true

Position? named

Default value None

Accept pipeline input? True (ByValue)

Accept wildcard characters? false

-ResourceGroupName <System.String>

Name of resource group.

Required? true

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Throughput <System.Nullable`1[System.Int32]>

The throughput of SQL container (RU/s). Default value is 400.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false

Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

Microsoft.Azure.Commands.CosmosDB.Models.PSSqlDatabaseGetResults

OUTPUTS

Microsoft.Azure.Commands.CosmosDB.Models.PSThroughputSettingsGetResults

NOTES

----- Example 1 -----

```
Update-AzCosmosDBSqlContainerThroughput -AccountName "myAccountName" -ResourceGroupName  
"myResourceGroupName" -DatabaseName "myDatabaseName" -Name "myContainerName"  
-Throughput $updatedThroughputValue
```

```
Name           : mxGp  
Id             :  
/subscriptions/{mySubscriptionId}/resourceGroups/{myResourceGroupName}/providers/Microsoft.DocumentDB/databaseAc  
counts/{myAccountName}/sqlDatabases  
es/{myDatabaseName}/containers/{myContainerName}/throughputSettings/default  
Throughput     : {updatedThroughputValue}  
MinimumThroughput : 400  
OfferReplacePending :
```

----- Example 2 -----

```
Update-AzCosmosDBSqlContainerThroughput -AccountName myAccountName -AutoscaleMaxThroughput <Int32>  
-DatabaseName myDatabaseName -Name dbname -ResourceGroupName rg1
```

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.cosmosdb/update-azcosmosdbsqlcontainerthroughput>

