



Windows PowerShell Get-Help on Cmdlet 'Update-AzRecoveryServicesAsrProtectionContainerMapping'

PS:\>Get-HELP Update-AzRecoveryServicesAsrProtectionContainerMapping -Full

NAME

Update-AzRecoveryServicesAsrProtectionContainerMapping

SYNOPSIS

Update the Azure site recovery protection container mapping.

SYNTAX

```
Update-AzRecoveryServicesAsrProtectionContainerMapping -AutomationAccountId <System.String> -AzureToAzure
[-DefaultProfile
    <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -EnableAutoUpdate
-InputObject
    <Microsoft.Azure.Commands.RecoveryServices.SiteRecovery.ASRProtectionContainerMapping> [-Confirm] [-WhatIf]
[<CommonParameters>]
```

```
Update-AzRecoveryServicesAsrProtectionContainerMapping -AzureToAzure [-DefaultProfile
    <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -DisableAutoUpdate
-InputObject
    <Microsoft.Azure.Commands.RecoveryServices.SiteRecovery.ASRProtectionContainerMapping> [-Confirm] [-WhatIf]
[<CommonParameters>]
```

DESCRIPTION

The Update-AzRecoveryServicesAsrProtectionContainerMapping cmdlet updates the specified Azure Site Recovery protection container mapping.

PARAMETERS

-AutomationAccountId <System.String>

Specifies the automation accountId used for auto update.

Required? true

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-AzureToAzure <System.Management.Automation.SwitchParameter>

Specifies Azure to Azure protection container.

Required? true

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-DisableAutoUpdate <System.Management.Automation.SwitchParameter>

Switch parameter to disable auto update.

Required? true

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-EnableAutoUpdate <System.Management.Automation.SwitchParameter>

Switch parameter to enable auto update.

Required? true

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-InputObject <Microsoft.Azure.Commands.RecoveryServices.SiteRecovery.ASRProtectionContainerMapping>

Object for protection container mapping.

Required? true

Position? named

Default value None

Accept pipeline input? True (ByValue)

Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false

Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

Microsoft.Azure.Commands.RecoveryServices.SiteRecovery.ASRProtectionContainerMapping

OUTPUTS

Microsoft.Azure.Commands.RecoveryServices.SiteRecovery.ASRJob

NOTES

----- Example 1 -----

```
Update-AzRecoveryServicesAsrProtectionContainerMapping -InputObject $ASRProtectionContainerMapping  
-AzureToAzure -DisableAutoUpdate
```

Start the operation to disable auto update for container.

----- Example 2 -----

```
Update-AzRecoveryServicesAsrProtectionContainerMapping -InputObject $ASRProtectionContainerMapping  
-AzureToAzure -EnableAutoUpdate -AutomationAccountId  
$automationAccountId
```

Start the operation to disable enable auto update for container.

RELATED LINKS

Online

Version:

<https://learn.microsoft.com/powershell/module/az.recoveryservices/update-azrecoveryservicesasrprotectioncontainermapping>