



Windows PowerShell Get-Help on Cmdlet 'Update-AzServiceFabricDurability'

PS:\>Get-HELP Update-AzServiceFabricDurability -Full

NAME

Update-AzServiceFabricDurability

SYNOPSIS

Update the durability tier or VmSku of a node type in the cluster.

SYNTAX

```
Update-AzServiceFabricDurability [-ResourceGroupName] <System.String> [-Name] <System.String> [-DefaultProfile  
    <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -DurabilityLevel  
{Bronze | Silver | Gold} -NodeType <System.String> [-Sku  
    <System.String>] [-Confirm] [-WhatIf] [<CommonParameters>]
```

DESCRIPTION

Use Update-AzServiceFabricDurability to update durability or SKU of the cluster.

PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with azure.

Required?	false
Position?	named
Default value	None
Accept pipeline input?	False
Accept wildcard characters?	false

-DurabilityLevel <Microsoft.Azure.Commands.ServiceFabric.Models.DurabilityLevel>

Specify durability level.

Required?	true
Position?	named
Default value	None
Accept pipeline input?	True (ByValue)
Accept wildcard characters?	false

-Name <System.String>

Specify the name of the cluster.

Required?	true
Position?	1
Default value	None
Accept pipeline input?	True (ByPropertyName)
Accept wildcard characters?	false

-NodeType <System.String>

Specify Service Fabric node type name.

Required?	true
Position?	named
Default value	None
Accept pipeline input?	True (ByValue)

Accept wildcard characters? false

-ResourceGroupName <System.String>

Specifies the name of the resource group.

Required? true

Position? 0

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-Sku <System.String>

Specify the SKU of the node type.

Required? false

Position? named

Default value None

Accept pipeline input? True (ByValue)

Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false

Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

System.String

Microsoft.Azure.Commands.ServiceFabric.Models.DurabilityLevel

OUTPUTS

Microsoft.Azure.Commands.ServiceFabric.Models.PSCluster

NOTES

----- Example 1 -----

Update-AzServiceFabricDurability -ResourceGroupName 'Group1' -Name 'Contoso01SFCluster' -DurabilityLevel Silver
-NodeType nt1

This command changes durability tier of the NodeType 'nt1' to silver.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.servicefabric/update-azservicefabricdurability>