

Windows 10 Help on Commands

C:\>HELP WMIC

WMIC is deprecated.

[global switches] <command>

The following global switches are available:

/NAMESPACE Path for the namespace the alias operate against.

/ROLE Path for the role containing the alias definitions.

/NODE Servers the alias will operate against.

/IMPLEVEL Client impersonation level.

/AUTHLEVEL Client authentication level.

/LOCALE Language id the client should use.

/PRIVILEGES Enable or disable all privileges.

/TRACE Outputs debugging information to stderr.

/RECORD Logs all input commands and output.

Windows 10 Help on Commands

/FAILFAST Sets or resets the FailFast mode.

/USER User to be used during the session.

/PASSWORD Password to be used for session login.

/OUTPUT Specifies the mode for output redirection.

/APPEND Specifies the mode for output redirection.

/AGGREGATE Sets or resets aggregate mode.

/AUTHORITY Specifies the <authority type> for the connection.

/?:<BRIEF|FULL> Usage information.

For more information on a specific global switch, type: switch-name /?

The following alias/es are available in the current role:

ALIAS - Access to the aliases available on the local system

BASEBOARD - Base board (also known as a motherboard or system board) management.

BIOS - Basic input/output services (BIOS) management.

BOOTCONFIG - Boot configuration management.

Windows 10 Help on Commands

CDROM

- CD-ROM management.

COMPUTERSYSTEM

- Computer system management.

CPU

- CPU management.

CSPRODUCT

- Computer system product information from SMBIOS.

DATAFILE

- DataFile Management.

DCOMAPP

- DCOM Application management.

DESKTOP

- User's Desktop management.

DESKTOPMONITOR

- Desktop Monitor management.

DEVICEMEMORYADDRESS

- Device memory addresses management.

DISKDRIVE

- Physical disk drive management.

DISKQUOTA

- Disk space usage for NTFS volumes.

DMACHANNEL

- Direct memory access (DMA) channel management.

ENVIRONMENT

- System environment settings management.

FSDIR

- Filesystem directory entry management.

GROUP

- Group account management.

IDECONTROLLER

- IDE Controller management.


IRQ

- Interrupt request line (IRQ) management.

Windows 10 Help on Commands

JOB	- Provides access to the jobs scheduled using the schedule service.
LOADORDER	- Management of system services that define execution dependencies.
LOGICALDISK	- Local storage device management.
LOGON	- LOGON Sessions.
MEMCACHE	- Cache memory management.
MEMORYCHIP	- Memory chip information.
MEMPHYSICAL	- Computer system's physical memory management.
NETCLIENT	- Network Client management.
NETLOGIN	- Network login information (of a particular user) management.
NETPROTOCOL	- Protocols (and their network characteristics) management.
NETUSE	- Active network connection management.
NIC	- Network Interface Controller (NIC) management.
NICCONFIG	- Network adapter management.
NTDOMAIN	- NT Domain management.
NTEVENT	- Entries in the NT Event Log.
NTEVENTLOG	- NT eventlog file management.
ONBOARDDEVICE	- Management of common adapter devices built into the motherboard

Windows 10 Help on Commands



OS	- Installed Operating System/s management.
PAGEFILE	- Virtual memory file swapping management.
PAGEFILESET	- Page file settings management.
PARTITION	- Management of partitioned areas of a physical disk.
PORT	- I/O port management.
PORTCONNECTOR	- Physical connection ports management.
PRINTER	- Printer device management.
PRINTERCONFIG	- Printer device configuration management.
PRINTJOB	- Print job management.
PROCESS	- Process management.
PRODUCT	- Installation package task management.
QFE	- Quick Fix Engineering.
QUOTASETTING	- Setting information for disk quotas on a volume.
RDACCOUNT	- Remote Desktop connection permission management.
RDNIC	- Remote Desktop connection management on a specific network adapter.
RDPERMISSIONS	- Permissions to a specific Remote Desktop connection.

Windows 10 Help on Commands

- RECOVEROS - Information that will be gathered from memory when the operating system fails.
- REGISTRY - Computer system registry management.
- SCSICONTROLLER - SCSI Controller management.
- SERVER - Server information management.
- SERVICE - Service application management.
- SHADOWCOPY - Shadow copy management.
- SHADOWSTORAGE - Shadow copy storage area management.
- SHARE - Shared resource management.
- SOFTWAREELEMENT - Management of the elements of a software product installed on a system.
- SOFTWAREFEATURE - Management of software product subsets of SoftwareElement.
- SOUNDDEV - Sound Device management.
- STARTUP - Management of commands that run automatically when users log onto the computer system.
- SYSACCOUNT - System account management.
- SYSDRIVER - Management of the system driver for a base service.
- SYSTEMENCLOSURE - Physical system enclosure management.

Windows 10 Help on Commands

SYSTEMSLOT - Management of physical connection points including ports, slots and peripherals, and proprietary connections points.

TAPEDRIVE - Tape drive management.

TEMPERATURE - Data management of a temperature sensor (electronic thermometer).

TIMEZONE - Time zone data management.

UPS - Uninterruptible power supply (UPS) management.

USERACCOUNT - User account management.

VOLTAGE - Voltage sensor (electronic voltmeter) data management.

VOLUME - Local storage volume management.

VOLUMEQUOTASETTING - Associates the disk quota setting with a specific disk volume.

VOLUMEUSERQUOTA - Per user storage volume quota management.

WMISET - WMI service operational parameters management.

For more information on a specific alias, type: alias /?

CLASS - Escapes to full WMI schema.

PATH - Escapes to full WMI object paths.

Windows 10 Help on Commands

QUIT/EXIT - Exits the program.

For more information on CLASS/PATH/CONTEXT, type: (CLASS | PATH | CONTEXT) /?

