



Rocky Enterprise Linux 9.2 Manual Pages on command 'sane-hpsj5s.5'

C:\>man sane-hpsj5s.5

sane-hpsj5s(5) SANE Scanner Access Now Easy sane-hpsj5s(5)

NAME

sane-hpsj5s - SANE backend for HP ScanJet 5S sheet-fed scanner

DESCRIPTION

The sane-hpsj5s library implements a SANE (Scanner Access Now Easy) backend that provides access to a parallel port Hewlett-Packard ScanJet 5S scanner.

IMPORTANT: this is alpha code. Don't expect this to work correctly. Many functions are missing, others contain errors. In some cases, your computer might even hang. It cannot be excluded (although I consider it extremely improbable) that your scanner will be damaged.

LIMITATIONS: For now this backend works only on Linux. This limitation is due to dependence on the libieee1284 library. If your system supports libieee1284 too, this backend should work. If you ported libieee1284 for your platform, please let me know. Your system should support EPP (or EPP+ECP) mode to operate this scanner. Future versions will support ECP and SPP (Nibble and Byte) modes also. It's planned to support scanners not only at daisy-chain position 0, but anywhere. Support for multiple scanners could be implemented too.

Current version implements only gray scale scanning. True Color and B/W modes are not supported for now.

That said, TESTERS ARE WELCOME. Send your bug reports and comments to Max Vorobiev <pcwizard@yandex.ru>.

DEVICE NAMES

This backend expects device names of the form:

special

Where special is the parallel port name in form, libieee1284 expects. It seems to be system dependent. Under Linux it's parport0, parport1, etc.

CONFIGURATION

The contents of the hpsj5s.conf file is a list of parport names that correspond to HP ScanJet 5S scanners. Empty lines and lines starting with a hash mark (#) are ignored. Only one device name can be listed in hpsj5s.conf for this moment. Future versions will support daisy chain selection.

TIPS

It seems that HP ScanJet 5S scanner uses software noise correction. This feature is not implemented for now. So does gamma correction and calibration. I'll handle it in future versions. Native resolution for this scanner is 300 DPI. Other modes could be jagged in some ways.

FILES

@CONFIGDIR@/hpsj5s.conf

The backend configuration file (see also description of SANE_CONFIG_DIR below).

@LIBDIR@/libsane-hpsj5s.a

The static library implementing this backend.

@LIBDIR@/libsane-hpsj5s.so

The shared library implementing this backend (present on systems that support dynamic loading).

ENVIRONMENT

SANE_CONFIG_DIR

This environment variable specifies the list of directories that may contain the configuration file. Under UNIX, the directories are separated by a colon (:), under OS/2, they are separated by a semi-colon (;). If this variable is not set, the configuration file is searched in two default directories: first, the current working directory (".") and then in @CONFIGDIR@. If the value of the environment variable ends with the directory separator character, then the default directories are searched after the explicitly specified directories. For example, setting SANE_CONFIG_DIR to

"/tmp/config:" would result in directories "tmp/config", ".", and "@CON?
FIGDIR@" being searched (in this order).

SEE ALSO

sane(7)

<http://hpsj5s.sourceforge.net>

<http://cyberelk.net/tim/libieee1284>

AUTHOR

Max Vorobiev

Man page mostly based on canon.man

@PACKAGEVERSION@

13 Jul 2008

sane-hpsj5s(5)