



Full credit is given to the above companies including the Operating System (OS) that this PDF file was generated!

Rocky Enterprise Linux 9.2 Manual Pages on command 'foo2slx-wrapper.1'

\$ man foo2slx-wrapper.1

foo2slx-wrapper(1)

General Commands Manual

foo2slx-wrapper(1)

NAME

foo2slx-wrapper - Convert Postscript into a SLX printer stream

SYNOPSIS

foo2slx-wrapper [options] [ps-file]

DESCRIPTION

foo2slx-wrapper is a Foomatic compatible printer wrapper for the foo2slx printer driver.

This script reads a Postscript ps-file or standard input and converts it to Software Imag?

ing K.K. SLX printer format for driving the Lexmark C500 network color laser printer and

other SLX-based printers.

This script can be used in a standalone fashion, but is intended to be called from a

printer spooler system which uses the Foomatic printer database.

COMMAND LINE OPTIONS

Normal Options

These are the options used to select the parameters of a print job that are usually controlled on a per job basis.

-c Print in color (else monochrome).

-m media

Media code to send to printer [0].

?????????????????????????

Media SLX

?????????????????????????

plain 0

transparency 1

labels 2

thick1 3

envelope1 4

thin 5

thick2 6

envelope2 7

middle 8

special 9

-p paper

Paper size code to send to printer [6].

????????????????????????????????????

? 6 letter ? 2 A4 ?

? 9 legal ? 4 B5 ?

? 8 executive ? 5 B5iso ?

?10 env #10 ? 11 env DL ?

????????????????????????????????????

-n copies

Number of copies [1].

-r xresyres

Set device resolution in pixels/inch [1200x600].

-s source

Source (Input Slot) code to send to printer [0].

????????????????????????????????

?0 auto ? 1 cassette1 ?

????????????????????????????????

-2 -3 -4 -5 -6 -8 -9 -10 -12 -14 -15 -16 -18

Print in N-up. Requires the psutils package.

-o orient

Orientation used for N-up.

Portrait -op (normal)

Landscape -ol (rotated 90 degrees anticlockwise)

Seascape -os (rotated 90 degrees clockwise)

Printer Tweaking Options

These are the options used to customize the operation of foo2slx for a particular printer.

-u xoffxyoff

Set the offset of the start of the printable region from the upper left corner, in pixels [varies with paper size]. The defaults should work on the 2200DL and 2300DL, and have not been tested on any other printers.

-l xoffxyoff

Set the offset of the end of the printable region from the lower right corner, in pixels [varies with paper size]. The defaults should work on the 2200DL and 2300DL, and have not been tested on any other printers.

-L mask

Send the logical clipping values from -u/-l in the ZjStream. foo2slx-wrapper always runs Ghostscript with the ideal page dimensions, so that the scale of the image is correct, regardless whether or not the printer has unprintable regions.

This option is used to move the position of the clipped image back to where it belongs on the page. The default is to send the amount which was clipped by -u and -l, and should be good in most cases.

- 0 don't send any logical clipping amounts
- 1 only send Y clipping amount
- 2 only send X clipping amount
- 3 send both X and Y clipping amounts

Color Tweaking Options

These are the options used to control the quality of color output. Color correction is currently a WORK IN PROGRESS.

-g gsopts

Additional options to pass to Ghostscript, such as -g?-dDITHERPPI=nnn?, etc. This option may appear more than once.

-G profile.icm

Convert profile.icm to a Postscript color rendering dictionary (CRD) using foo2zjs-icc2ps and adjust the printer colors by using the Postscript setcolorrendering operator. (WORK IN PROGRESS).

-G gamma-file.ps

Prepend gamma-file.ps to the Postscript input to perform color correction using the

setcolortransfer Postscript operator. For example, the file might contain:

```
{0.333 exp} {0.333 exp} {0.333 exp} {0.333 exp} setcolortransfer
```

-I intent

Select profile intent from the ICM file. 0=Perceptual, 1=Colorimetric, 2=Satura?
tion, 3=Absolute. Default is 0 (perceptual).

Debugging Options

These options are used for debugging foo2slx and its wrapper.

-S plane

Output just a single color plane from a color print and print it on the black
plane. The default is to output all color planes.

1 Cyan

2 Magenta

3 Yellow

4 Black

-D level

Set Debug level [0].

EXAMPLES

Create a monochrome ZjStream from a Postscript document, examine it, and then print it us?
ing a RAW print queue:

```
foo2slx-wrapper testpage.ps > testpage.zm
slxdecode < testpage.zm
lpr -P raw testpage.zm
```

Create a color ZjStream stream from a Postscript document:

```
foo2slx-wrapper -c testpage.ps > testpage.zc
```

FILES

/usr/bin/foo2slx-wrapper

SEE ALSO

foo2slx(1), slxdecode(1)

AUTHOR

Rick Richardson <rick.richardson@comcast.net>

<http://foo2slx.rkkda.com/>