



## ***Rocky Enterprise Linux 9.2 Manual Pages on command 'vcs.4'***

**C:~>man vcs.4**

VCS(4)                      Linux Programmer's Manual                      VCS(4)

### NAME

vcs, vcsa - virtual console memory

### DESCRIPTION

`/dev/vcs0` is a character device with major number 7 and minor number 0, usually with mode 0644 and ownership root:tty. It refers to the memory of the currently displayed virtual console terminal.

`/dev/vcs[1-63]` are character devices for virtual console terminals, they have major number 7 and minor number 1 to 63, usually mode 0644 and ownership root:tty.

`/dev/vcsa[0-63]` are the same, but using unsigned shorts (in host byte order) that include attributes, and prefixed with four bytes giving the screen dimensions and cursor position: lines, columns, x, y. (x = y = 0 at the top left corner of the screen.)

When a 512-character font is loaded, the 9th bit position can be fetched by applying the `ioctl(2)` `VT_GETHIFONTMASK` operation (available in Linux kernels 2.6.18 and above) on `/dev/tty[1-63]`; the value is returned in the unsigned short pointed to by the third `ioctl(2)` argument.

These devices replace the `screendump` `ioctl(2)` operations of `ioctl_console(2)`, so the system administrator can control access using filesystem permissions.

The devices for the first eight virtual consoles may be created by:

```
for x in 0 1 2 3 4 5 6 7 8; do
```

```
    mknod -m 644 /dev/vcs$x c 7 $x;
```

```
mknod -m 644 /dev/vcsa$c c 7 $[$x+128];
```

done

```
chown root:tty /dev/vcs*
```

No ioctl(2) requests are supported.

## FILES

```
/dev/vcs[0-63]
```

```
/dev/vcsa[0-63]
```

## VERSIONS

Introduced with version 1.1.92 of the Linux kernel.

## EXAMPLE

You may do a screendump on vt3 by switching to vt1 and typing

```
cat /dev/vcs3 >foo
```

Note that the output does not contain newline characters, so some processing may be required, like in

```
fold -w 81 /dev/vcs3 | lpr
```

or (horrors)

```
setterm -dump 3 -file /proc/self/fd/1
```

The /dev/vcsa0 device is used for Braille support.

This program displays the character and screen attributes under the cursor of the second virtual console, then changes the background color there:

```
#include <unistd.h>
```

```
#include <stdlib.h>
```

```
#include <stdio.h>
```

```
#include <fcntl.h>
```

```
#include <sys/ioctl.h>
```

```
#include <linux/vt.h>
```

```
int
```

```
main(void)
```

```
{
```

```
    int fd;
```

```
    char *device = "/dev/vcsa2";
```

```
    char *console = "/dev/tty2";
```

```
    struct {unsigned char lines, cols, x, y;} scrn;
```

```

unsigned short s;

unsigned short mask;

unsigned char attrib;

int ch;

fd = open(console, O_RDWR);

if (fd < 0) {
    perror(console);
    exit(EXIT_FAILURE);
}

if (ioctl(fd, VT_GETHIFONTMASK, &mask) < 0) {
    perror("VT_GETHIFONTMASK");
    exit(EXIT_FAILURE);
}

(void) close(fd);

fd = open(device, O_RDWR);

if (fd < 0) {
    perror(device);
    exit(EXIT_FAILURE);
}

(void) read(fd, &scrn, 4);

(void) lseek(fd, 4 + 2*(scrn.y*scrn.cols + scrn.x), SEEK_SET);

(void) read(fd, &s, 2);

ch = s & 0xff;

if (s & mask)
    ch |= 0x100;

attrib = ((s & ~mask) >> 8);

printf("ch=0x%03x attrib=0x%02x\n", ch, attrib);

s ^= 0x1000;

(void) lseek(fd, -2, SEEK_CUR);

(void) write(fd, &s, 2);

exit(EXIT_SUCCESS);
}

```

ioctl\_console(2), tty(4), ttyS(4), gpm(8)

## COLOPHON

This page is part of release 5.05 of the Linux man-pages project. A description of the project, information about reporting bugs, and the latest version of this page, can be found at <https://www.kernel.org/doc/man-pages/>.

Linux

2019-03-06

VCS(4)