Full credit is given to the above companies including the OS that this PDF file was generated!

Red Hat Enterprise Linux Release 9.2 Manual Pages on 'ECDSA_sign_ex.3ossl' command

$ man ECDSA_sign_ex.3ossl

ECDSA_SIG_NEW(3ossl) OpenSSL ECDSA_SIG_NEW(3ossl)

NAME

ECDSA_SIG_get0, ECDSA_SIG_get0_r, ECDSA_SIG_get0_s, ECDSA_SIG_set0,

ECDSA_SIG_new, ECDSA_SIG_free, ECDSA_size, ECDSA_sign, ECDSA_do_sign,

ECDSA_verify, ECDSA_do_verify, ECDSA_sign_setup, ECDSA_sign_ex,

ECDSA_do_sign_ex - low-level elliptic curve digital signature algorithm

(ECDSA) functions

SYNOPSIS

```
#include <openssl/ecdsa.h>
ECDSA_SIG *ECDSA_SIG_new(void);
void ECDSA_SIG_free(ECDSA_SIG *sig);
void ECDSA_SIG_get0(const ECDSA_SIG *sig, const BIGNUM **pr, const BIGNUM **ps);
const BIGNUM *ECDSA_SIG_get0_r(const ECDSA_SIG *sig);
const BIGNUM *ECDSA_SIG_get0_s(const ECDSA_SIG *sig);
int ECDSA_SIG_set0(ECDSA_SIG *sig, BIGNUM *r, BIGNUM *s);
```

The following functions have been deprecated since OpenSSL 3.0, and can

be hidden entirely by defining OPENSSL_API_COMPAT with a suitable

version value, see openssl_user_macros(7):

```
int ECDSA_size(const EC_KEY *eckey);
int ECDSA_sign(int type, const unsigned char *dgst, int dgstlen,
               unsigned char *sig, unsigned int *siglen, EC_KEY *eckey);
ECDSA_SIG *ECDSA_do_sign(const unsigned char *dgst, int dgst_len,
                         EC_KEY *eckey);
```

```
int ECDSA_verify(int type, const unsigned char *dgst, int dgstlen,
                 const unsigned char *sig, int siglen, EC_KEY *eckey);
int ECDSA_do_verify(const unsigned char *dgst, int dgst_len,
                    const ECDSA_SIG *sig, EC_KEY* eckey);
ECDSA_SIG *ECDSA_do_sign_ex(const unsigned char *dgst, int dgstlen,
                            const BIGNUM *kinv, const BIGNUM *rp,
                            EC_KEY *eckey);
int ECDSA_sign_setup(EC_KEY *eckey, BN_CTX *ctx, BIGNUM **kinv, BIGNUM **rp);
int ECDSA_sign_ex(int type, const unsigned char *dgst, int dgstlen,
                  unsigned char *sig, unsigned int *siglen,
                  const BIGNUM *kinv, const BIGNUM *rp, EC_KEY *eckey);
```

DESCRIPTION

ECDSA_SIG is an opaque structure consisting of two BIGNUMs for the r and s value of an ECDSA signature (see X9.62 or FIPS186-2).

ECDSA_SIG_new() allocates an empty ECDSA_SIG structure. Note: before OpenSSL 1.1.0 the: the r and s components were initialised.

ECDSA_SIG_free() frees the ECDSA_SIG structure sig.

ECDSA_SIG_get0() returns internal pointers the r and s values contained in sig and stores them in *pr and *ps, respectively. The pointer pr or ps can be NULL, in which case the corresponding value is not returned.

The values r, s can also be retrieved separately by the corresponding function ECDSA_SIG_get0_r() and ECDSA_SIG_get0_s(), respectively.

Non-NULL r and s values can be set on the sig by calling ECDSA_SIG_set0(). Calling this function transfers the memory management of the values to the ECDSA_SIG object, and therefore the values that have been passed in should not be freed by the caller.

See i2d_ECDSA_SIG(3) and d2i_ECDSA_SIG(3) for information about encoding and decoding ECDSA signatures to/from DER.

All of the functions described below are deprecated. Applications should use the higher level EVP interface such as EVP_DigestSignInit(3) or EVP_DigestVerifyInit(3) instead.

ECDSA_size() returns the maximum length of a DER encoded ECDSA signature created with the private EC key eckey. To obtain the actual

signature size use EVP_PKEY_sign(3) with a NULL sig parameter.

ECDSA_sign() computes a digital signature of the dgstlen bytes hash value dgst using the private EC key eckey. The DER encoded signatures is stored in sig and its length is returned in sig_len. Note: sig must point to ECDSA_size(eckey) bytes of memory. The parameter type is currently ignored. ECDSA_sign() is wrapper function for ECDSA_sign_ex() with kinv and rp set to NULL.

ECDSA_do_sign() is similar to ECDSA_sign() except the signature is returned as a newly allocated ECDSA_SIG structure (or NULL on error). ECDSA_do_sign() is a wrapper function for ECDSA_do_sign_ex() with kinv and rp set to NULL.

ECDSA_verify() verifies that the signature in sig of size siglen is a valid ECDSA signature of the hash value dgst of size dgstlen using the public key eckey. The parameter type is ignored.

ECDSA_do_verify() is similar to ECDSA_verify() except the signature is presented in the form of a pointer to an ECDSA_SIG structure.

The remaining functions utilise the internal kinv and r values used during signature computation. Most applications will never need to call these and some external ECDSA ENGINE implementations may not support them at all if either kinv or r is not NULL.

ECDSA_sign_setup() may be used to precompute parts of the signing operation. eckey is the private EC key and ctx is a pointer to BN_CTX structure (or NULL). The precomputed values or returned in kinv and rp and can be used in a later call to ECDSA_sign_ex() or ECDSA_do_sign_ex().

ECDSA_sign_ex() computes a digital signature of the dgstlen bytes hash value dgst using the private EC key eckey and the optional pre-computed values kinv and rp. The DER encoded signature is stored in sig and its length is returned in sig_len. Note: sig must point to ECDSA_size(eckey) bytes of memory. The parameter type is ignored.

ECDSA_do_sign_ex() is similar to ECDSA_sign_ex() except the signature is returned as a newly allocated ECDSA_SIG structure (or NULL on error).

RETURN VALUES

ECDSA_SIG_new() returns NULL if the allocation fails.

ECDSA_SIG_set0() returns 1 on success or 0 on failure.

ECDSA_SIG_get0_r() and ECDSA_SIG_get0_s() return the corresponding value, or NULL if it is unset.

ECDSA_size() returns the maximum length signature or 0 on error.

ECDSA_sign(), ECDSA_sign_ex() and ECDSA_sign_setup() return 1 if successful or 0 on error.

ECDSA_do_sign() and ECDSA_do_sign_ex() return a pointer to an allocated ECDSA_SIG structure or NULL on error.

ECDSA_verify() and ECDSA_do_verify() return 1 for a valid signature, 0 for an invalid signature and -1 on error. The error codes can be obtained by ERR_get_error(3).

EXAMPLES

Creating an ECDSA signature of a given SHA-256 hash value using the named curve prime256v1 (aka P-256).

First step: create an EC_KEY object (note: this part is not ECDSA specific)

```
 int ret;
 ECDSA_SIG *sig;
 EC_KEY *eckey;
 eckey = EC_KEY_new_by_curve_name(NID_X9_62_prime256v1);
 if (eckey == NULL)
     /* error */
 if (EC_KEY_generate_key(eckey) == 0)
     /* error */
```

Second step: compute the ECDSA signature of a SHA-256 hash value using ECDSA_do_sign():

```
 sig = ECDSA_do_sign(digest, 32, eckey);
 if (sig == NULL)
     /* error */
```

or using ECDSA_sign():

```
 unsigned char *buffer, *pp;
```

```
int buf_len;
buf_len = ECDSA_size(eckey);
buffer = OPENSSL_malloc(buf_len);
pp = buffer;
if (ECDSA_sign(0, dgst, dgstlen, pp, &buf_len, eckey) == 0)
    /* error */
```

Third step: verify the created ECDSA signature using ECDSA_do_verify():

```
ret = ECDSA_do_verify(digest, 32, sig, eckey);
```

or using ECDSA_verify():

```
ret = ECDSA_verify(0, digest, 32, buffer, buf_len, eckey);
```

and finally evaluate the return value:

```
if (ret == 1)
    /* signature ok */
else if (ret == 0)
    /* incorrect signature */
else
    /* error */
```

CONFORMING TO

ANSI X9.62, US Federal Information Processing Standard FIPS186-2 (Digital Signature Standard, DSS)

SEE ALSO

EC_KEY_new(3), EVP_DigestSignInit(3), EVP_DigestVerifyInit(3), EVP_PKEY_sign(3) i2d_ECDSA_SIG(3), d2i_ECDSA_SIG(3)

HISTORY

The ECDSA_size(), ECDSA_sign(), ECDSA_do_sign(), ECDSA_verify(), ECDSA_do_verify(), ECDSA_sign_setup(), ECDSA_sign_ex() and ECDSA_do_sign_ex() functions were deprecated in OpenSSL 3.0.

COPYRIGHT

3.0.7	2023-07-13	ECDSA_SIG_NEW(3ossl)