Full credit is given to the above companies including the OS that this PDF file was generated!

Red Hat Enterprise Linux Release 9.2 Manual Pages on 'EC_KEY_get_enc_flags.3ossl' command

$ man EC_KEY_get_enc_flags.3ossl

EC_KEY_GET_ENC_FLAGS(3ossl) OpenSSL EC_KEY_GET_ENC_FLAGS(3ossl)

NAME

EC_KEY_get_enc_flags, EC_KEY_set_enc_flags - Get and set flags for encoding EC_KEY structures

SYNOPSIS

```
#include <openssl/ec.h>

unsigned int EC_KEY_get_enc_flags(const EC_KEY *key);
void EC_KEY_set_enc_flags(EC_KEY *eckey, unsigned int flags);
```

DESCRIPTION

The format of the external representation of the public key written by i2d_ECPrivateKey() (such as whether it is stored in a compressed form or not) is described by the point_conversion_form. See EC_GROUP_copy(3) for a description of point_conversion_form.

When reading a private key encoded without an associated public key (e.g. if EC_PKEY_NO_PUBKEY has been used - see below), then d2i_ECPrivateKey() generates the missing public key automatically.

Private keys encoded without parameters (e.g. if EC_PKEY_NO_PARAMETERS has been used - see below) cannot be loaded using d2i_ECPrivateKey().

The functions EC_KEY_get_enc_flags() and EC_KEY_set_enc_flags() get and set the value of the encoding flags for the key. There are two encoding flags currently defined - EC_PKEY_NO_PARAMETERS and EC_PKEY_NO_PUBKEY. These flags define the behaviour of how the key is converted into ASN1 in a call to i2d_ECPrivateKey(). If EC_PKEY_NO_PARAMETERS is set then the public parameters for the curve are not encoded along with the private key. If EC_PKEY_NO_PUBKEY is set then the public key is not encoded along with the private key.

RETURN VALUES

EC_KEY_get_enc_flags() returns the value of the current encoding flags for the EC_KEY.

SEE ALSO

crypto(7), EC_GROUP_new(3), EC_GROUP_copy(3), EC_POINT_new(3), EC_POINT_add(3), EC_GFp_simple_method(3), d2i_ECPKParameters(3), d2i_ECPrivateKey(3)

COPYRIGHT