



Full credit is given to the above companies including the OS that this PDF file was generated!

Red Hat Enterprise Linux Release 9.2 Manual Pages on 'pthread_attr_getstacksize.3' command

\$ man pthread_attr_getstacksize.3

PTHREAD_ATTR_SETSTACKSIZE(3Linux Programmer's Manual) PTHREAD_ATTR_SETSTACKSIZE(3)

NAME

pthread_attr_setstacksize, pthread_attr_getstacksize - set/get stack

size attribute in thread attributes object

SYNOPSIS

```
#include <pthread.h>

int pthread_attr_setstacksize(pthread_attr_t *attr, size_t stacksize);

int pthread_attr_getstacksize(const pthread_attr_t *attr,
                             size_t *stacksize);
```

Compile and link with -pthread.

DESCRIPTION

The pthread_attr_setstacksize() function sets the stack size attribute of the thread attributes object referred to by attr to the value specified in stacksize.

The stack size attribute determines the minimum size (in bytes) that will be allocated for threads created using the thread attributes object attr.

The pthread_attr_getstacksize() function returns the stack size attribute of the thread attributes object referred to by attr in the buffer pointed to by stacksize.

RETURN VALUE

On success, these functions return 0; on error, they return a nonzero error number.

ERRORS

`pthread_attr_setstacksize()` can fail with the following error:

`EINVAL` The stack size is less than `PTHREAD_STACK_MIN` (16384) bytes.

On some systems, `pthread_attr_setstacksize()` can fail with the error

`EINVAL` if `stacksize` is not a multiple of the system page size.

VERSIONS

These functions are provided by glibc since version 2.1.

ATTRIBUTES

For an explanation of the terms used in this section, see `at?`

`tributes(7)`.

??

?Interface ? Attribute ? Value ?

??

?`pthread_attr_setstacksize()`, ? Thread safety ? MT-Safe ?

?`pthread_attr_getstacksize()` ? ? ?

??

CONFORMING TO

POSIX.1-2001, POSIX.1-2008.

NOTES

For details on the default stack size of new threads, see `pthread_creat?`

`ate(3)`.

A thread's stack size is fixed at the time of thread creation. Only the main thread can dynamically grow its stack.

The `pthread_attr_setstack(3)` function allows an application to set both the size and location of a caller-allocated stack that is to be used by a thread.

BUGS

As at glibc 2.8, if the specified `stacksize` is not a multiple of `STACK_ALIGN` (16 bytes on most architectures), it may be rounded down, in violation of POSIX.1, which says that the allocated stack will be at least `stacksize` bytes.

EXAMPLES

See `pthread_create(3)`.

SEE ALSO

getrlimit(2), pthread_attr_init(3), pthread_attr_setguardsize(3),
pthread_attr_setstack(3), pthread_create(3), pthreads(7)

COLOPHON

This page is part of release 5.10 of the Linux man-pages project. A description of the project, information about reporting bugs, and the latest version of this page, can be found at <https://www.kernel.org/doc/man-pages/>.

Linux

2020-06-09 PTHREAD_ATTR_SETSTACKSIZE(3)