

NAME

XtAppSetFallbackResources – set fallback resources

SYNTAX

```
void XtAppSetFallbackResources(XtAppContext app_context, String* specification_list);
```

ARGUMENTS

app_context Specifies the application context.

specification_list Specifies a NULL-terminated list of resource specifications to pre-load the database, or NULL.

DESCRIPTION

Each entry in *specification_list* points to a string in the format **XrmPutLineResource**. following a call to **XtAppSetFallbackResources**, when a resource database is being created for a particular screen and the In-
trinsics are not able to find or read an application-specific class resource file and if *specification_list* is not
NULL the resource specification in *specification_list* will be merged into the screen resource database in
place of the application-specific class resource file. **XtAppSetFallbackResources** is not required to copy
specification_list; the caller must ensure that the contents of the list and the strings addressed by the list re-
main valid until all displays are initialized or until **XtAppSetFallbackResources** is called again. The value
NULL for *specification_list* removes any previous fallback resource specification for the application con-
text. The intended use for fallback resources is to provide a minimal number of resources that will make
the application usable (or at least terminate with helpful diagnostic messages) when some problem exists in
finding and loading the application defaults file.

SEE ALSO

X Toolkit Intrinsic – C Language Interface

Xlib – C Language X Interface